
PC Software

Download GENBOLT CAM for Windows/MacBook from genbolt.com/blog/downloads.



1. Enter detailed settings, account: admin, Password: no need to fill in.




- 2: 1 Click the "Settings" button.
 - **2**Click "Input UID".
 - (3) Input UID manually. (UID is on the label of camera)
 - **4** Enter the default password "admin". (If you have changed your password, please enter the changed password.)
 - 5Click let to view. If offline, right click on the camera "connect device".

Switch into Wi-Fi Connection




- 1 After completing the wired connection, click the "Settings" button.
- **2**Click "Parameter settings".
- 3Select the camera UID.
- 4Click "Wifi".
- 5Click "Search".
- 6Select your wifi.
- Input wifi password.
- 8 Apply.
- * Wait it about 1 min, when camera online unplug LAN cable and it have connected with wifi.
- * If finished Wi-Fi switch in app, no need to setting again in pc.

If No Image After Adding



- 1 Double click the UID.
- **2**To protect your privacy, please change the camera's default password "admin" to a new password.
- The new password is limited to 8 letters and numbers. After setting the new password, you can view the live image.


Software Main Interface



- 1 Menu of main functions:
- Preview
- Add device automatically
- Play the local recordings
- Play the TF card recordings
- **2**Camera added

[AABB-360721-DEDFF] -- Connected camera UID. (Note: If show camera offline please right click camera and


- Detailed settings
- **Logs**
- **O** Log out




click connnect device; If not show up camera image, please drag the camera UID under Region select to right box).

Image Quality Selection

Right-click the UID of the camera and select "Quality:Max" for best video performance. Swich to "Quality:Min" for smoother play.




Save Recordings (to TF card)



- 1 Click the "Settings" button.
- Click "Parameter settings".
- 3Select the camera UID.
- 4Click "SD Card".
- 5Click "Enable the plan of record".
- 6Set the duration of recording, select the schedule you want to record.
- Click "Apply", and the setting up will be finished.

Save Recordings (to Hard Disk)



- 1 Click the "Settings" button.
- Click "Record Management".
- Select the camera UID.
- 4Click "SD Card".

IP Address Change



- 1 Click the "Settings" button.
- Click Parameter settings.
- ③Please select the camera UID you want to change.